

### Konfiguration DI-106 / DI-300 für einen Internet-Zugang

#### Folgende fett gedruckte Punkte müssen angegeben sein:

#### **D-Link Corporation**

#### DI-106/300 Main Menu

#### Getting Started

- 1. General Setup
- 2. ISDN Setup
- 3. Ethernet Setup
- 4. Internet Access Setup

#### Advanced Management

- 21. Filter Set Configuration
- 23. System Security
- 24. System Maintenance

#### Advanced Applications

- 11. Remote Node Setup
- 12. Static Routing Setup
- 13. Default Dial-in Setup
- 14. Dial-in User Setup

- 99. Exit

Enter Menu Selection Number:

### Menu 1 - General Setup

System Name=  
Location=  
Contact Person's Name=

Route IP= **Yes**

Press ENTER to Confirm or ESC to Cancel:

### Menu 2 - ISDN Setup

Switch Type: **DSS-1**

B Channel Usage= **Switch/Switch**

ISDN Data = **Router Telefonnummer** Subaddress=

Dial Prefix to Access Outside Line= **0 (nur für Amtsholung)**

PABX Number (Include S/T Bus Number)=

Incoming Phone Number Matching= **Don't Care**

Press ENTER to Confirm or ESC to Cancel:

Press Space Bar to Toggle.

### Menu 3.2 - TCP/IP and DHCP Ethernet Setup

DHCP Setup:

DHCP= None

Client IP Pool Starting Address= N/A

Size of Client IP Pool= N/A

Primary DNS Server= N/A

Secondary DNS Server= N/A

TCP/IP Setup:

IP Address= **192.168.0.1 (lokale IP-Adresse des Routers)**

IP Subnet Mask= **wird vorgegeben**

RIP Direction= **None**

Version= RIP-2B

Press ENTER to Confirm or ESC to Cancel:

Press Space Bar to Toggle.

## Menu 4 - Internet Access Setup

ISP's Name= **(z.B. T-Online)**

ISP IP Addr=

Pri Phone #= **Telefonnummer des Providers (T-Online = 0191011)**

Sec Phone #=

My Login= **Anschlußkennung****Für T-Online Kunden:****<Kennung><Telefonnummer>#<0001>**My Password= **\*\*\*\*\***Single User Account= **Yes**IP Addr= **0.0.0.0**Server IP Addr= **0.0.0.0**

Telco Option:

Transfer Type= **64K**Multilink= **Off**

Press ENTER to Confirm or ESC to Cancel:

Konfiguration Workstation (Win95)

Folgende Punkte müssen in den TCP/IP – Eigenschaften vorhanden sein





